

# Software Update Instructions for your CarDAQPlus 4 Product


1. Double Click on Zip file downloaded from OpusIVS website in the Download Directory
2. Double click on “Cardaqplu4\_0404\_0500\_setup.exe” menu

Name	Type	Compressed size	Password ...	Size	Ratio	Date modified
drivers	File folder					6/2/2025 1:00 PM
cardaqplus4_0404_0500_setup.exe	Application	55,341 KB	No	55,845 KB	1%	5/20/2025 2:05 PM
dotNetFx40_Full_x86_x64.exe	Application	49,185 KB	No	49,268 KB	1%	3/18/2010 9:44 PM

3. Select “**Extract all**” from the Compressed (zipped) Folders.



4. Select the unzipped folder from your downloads directory.



5. Select Cardaqplus4\_0404\_0500\_Setup.exe




6. Connect your CarDAQ Plus 4 device to your PC using the provided USB cable and make sure your CarDAQ Plus 4 device is connected to the wall plug.




# Software Update Instructions for your CarDAQPlus 4 Product

7. Check the I accept the terms in the license agreement box and select Install.



8. Select Exist from the Successfully Installed message.



9. Run **J2534 Toolbox** software and select HELP, ABOUT DRIVER from the main menu. Confirm the J2534 drivers were installed correctly (1.2.15.0). also to confirm the firmware within the CarDAQ Pro device is updated to the latest version (1.2.10.0)

